

cfgridcolumn

Description

Used with cfgrid in a cfform, you use cfgridcolumn to specify column data in a cfgrid control. Font and alignment attributes used in cfgridcolumn override any global font or alignment settings defined in cfgrid.

Category

Other

Implemented

Usage Syntax

```
name="String"  
[mask="String"]  
[header="String"]  
[width="number"]  
[font="String"]  
[fontSize="number"]  
[italic="Boolean"]  
[bold="Boolean"]  
[textColor="String"]  
[bgColor="String"]  
[href="String"]  
[hrefKey="String"]  
[target="String"]  
[select="Boolean"]  
[display="Boolean"]  
[type="String"]  
[headerFont="String"]  
[headerFontSize="number"]  
[headerItalic="Boolean"]  
[headerBold="Boolean"]  
[headerTextColor="String"]  
[dataAlign="String"]  
[headerAlign="String"]
```

Contents

- [cfgridcolumn](#)
- [Description](#)
- [Category](#)
- [Implemented](#)
- [Usage Syntax](#)
- [Attributes](#)
- [Example Usage](#)

```
[numberFormat="String"]
[values="String"]
[valuesDisplay="String"]
[valuesDelimiter="String"]
/>
```

[] = *Optional attribute*

Attributes

Name	Type	Required	Default	Description
name	String	Yes		A name for the grid column element. If the grid uses a query, the column name must specify the name of a query column.
mask	String	No		
header	String	No		Text for the column header. The value of header is used only when the cfgrid colHeaders attribute is Yes (or omitted, since it defaults to Yes).
width	number	No		The width of the column, in pixels. Default is the width of the column head text.
font	String	No		Font name to use for data in the column. Defaults is the font specified by cfgrid.
fontSize	number	No		Font size for text in the column. Default is the font specified by cfgrid.
italic	Boolean	No		Yes or No. Yes displays all grid control text in italic. Default is as specified by the corresponding attribute of cfgrid.
bold	Boolean	No		Yes or No. Yes displays all grid control text in boldface. Default is as specified by the corresponding attribute of cfgrid.
textColor	String	No		Color value for grid element text in the grid column, or an expression you can use to manipulate text color in grid column elements. Valid color entries are: black (default), magenta, cyan, orange, arkgray, pink, gray, white, lightgray, yellow

bgColor	String	No	Color value for the background of the grid column, or an expression you can use to manipulate grid column background color. Valid color entries are: black, magenta, cyan, orange, darkgray, pink, gray, white (default), lightgray, yellow.
href	String	No	URL to associate with the grid item. You can specify a URL that is relative to the current page
hrefKey	String	No	The name of a query column when the grid uses a query. The column specified becomes the Key regardless of the select mode for the grid.
target	String	No	The name of the frame in which to open the link specified in href.
select	Boolean	No	Yes or No. Yes lets end users select a column in a grid control. When No, the column cannot be edited, even if the cfgrid insert or delete attributes are enabled. The value of the select attribute is ignored if the cfgrid selectMode attribute is set to Row or Browse.
display	Boolean	No	Yes or No. Use to hide columns. Default is Yes to display the column.
type	String	No	
headerFont	String	No	Font to use for the column header. Default is as specified by the corresponding attribute of cfgrid.
headerFontSize	number	No	Font size to use for the column header, in pixels. Default is as specified by the corresponding attribute of cfgrid.
headerItalic	Boolean	No	Yes or No. Yes displays column header text in italic. Default is as specified by the corresponding attribute of cfgrid.
headerBold	Boolean	No	Yes or No. Yes displays header text in boldface. Default is as specified by the corresponding attribute of cfgrid.
headerTextColor	String	No	Color value for the grid control column header text. Entries are: black (default), magenta, cyan, orange, darkgray, pink, gray, white, lightgray, yellow.
dataAlign	String	No	Alignment for column data. Entries are: left, center, or right. Default is as specified by cfgrid.

headerAlign	String	No	Alignment for the column header text. Default is as specified by cfgrid.
numberFormat	String	No	The format for displaying numeric data in the grid. For information about mask characters, see "numberFormat mask characters".
values	String	No	Formats cells in the column as drop down list boxes. lets end users select an item in a drop down list. Use the values attribute to specify the items you want to appear in the drop down list.
valuesDisplay	String	No	Used to map elements specified in the values attribute to a string of your choice to display in the drop down list. Enter comma separated strings and/or numeric range(s).
valuesDelimiter	String	No	Character to use as a delimiter in the values and valuesDisplay attributes. Default is "," (comma).

Example Usage